

IRB-File-IrbAcs-SDK

Version 2

Documentation

State: 20/12/2017

Table of contents

1	Introduction.....	1
2	Data structures	2
2.1	IRB-header structures	2
2.2	IRB-Calib structure	3
2.3	Correction data structure.....	3
3	List of DLL-Functions.....	4
3.1	version.....	4
3.2	loadIRB.....	4
3.3	unloadIRB	4
3.4	getFrameCount	5
3.5	getIRBIndices.....	5
3.6	getFrameNumber	5
3.7	setFrameNumber	6
3.8	getFrameNbByArrayIdx.....	6
3.9	setFrameNbByArrayIdx.....	6
3.10	getTempBBXY	7
3.11	getTempXY	7
3.12	getDigValXY	7
3.13	readPixelData.....	8
3.14	readIRBData	8
3.15	readIRBDataUncompressed	8
3.16	convertPixelToKelvin.....	9
3.17	getParam.....	10
3.18	setParam.....	11
3.19	getParamS	11
3.20	getMilliTime	11
3.21	getFrameTimeStamp	12
3.22	getIRBCalibData*	13
3.23	getIRBHeader*	13
3.24	setIRBHeader*	14
3.25	saveSingleFrame	14
3.26	exportVisBitmap	14
3.27	audioComment.....	15

1 Introduction

The software implemented for infrared cameras saves its data in indexed files, what allows a fast and comfortable access. To simplifying handling for external software a SDK was created, which carries out the direct access to IRB files. The name of this library is IRBACS_xx.DLL or in linux systems libirbacs_xx.so and it allows especially the access to thermographic relevant properties of the in IRB-files saved infrared images. The intention of the SDK consist in providing the thermographic data for customer applications. With that passed data a user can develop his own application environment. Feeding back the changed data in the InfraTec software environment is not a primary aim of this SDK.

The range of functionality comprises access to the temperature data, header structure und temperature relevant correction parameters. Changed frames can be saved as single frame irb-file and in a limited range are manipulation of header data possible.

The following operating systems are supported:

Windows beginning with XP - 32 bit:	irbacs_w32.dll
Windows beginning with 7 - 64 bit:	irbacs_w64.dll
Linux – 32 bit:	libirbacs_l32.so
Linux – 64 bit:	libirbacs_l64.so

The following restrictions apply :

- Windows 64 bit : Compressed IRB-files of VarioCAM HD can not decompressed by 64-bit version of irbacs.dll.
- Resolution enhanced frames are not calculated, only the original camera resolution is available.

For real time access to data of camera systems exist another SDK (IRBGRAB-SDK), what is actually only as a 32-bit-dll available.

2 Data structures

All data structures are without empty bytes for alignment (packed). Type Boolean is represented as byte.

2.1 IRB-header structures

This structure describes with its substructures image and temperature relevant informations of IRB-format.

TIRBgeomInfo = packed record

```
    pixelFormat      : Word;  
    compression      : Word;  
    imgWidth         : Word;  
    mgHeight         : Word;  
    upperLeftX       : Word;  
    upperLeftY       : Word;  
    firstValidX       : Word;  
    lastValidX        : Word;  
    firstValidY       : Word;  
    lastValidY        : Word;  
    position          : Single;
```

end;

TIRBobjPars = packed record

```
    emissivity        : Single;  
    objDistance        : Single;  
    ambTemp           : Single;  
    absoConst          : Single;  
    pathTemp           : Single;  
    version            : LongInt;
```

end;

TIRBCalibPars1 = packed record

```
    cbData             : array[0..1567] of byte;
```

end;

TIRBImageInfo = packed record

```
    level              : Single;  
    span               : Single;  
    imgTime            : TDateTime;  
    imgMilliTime       : Single; // Milliseconds  
    imgAccu            : Word;  
    imageComment       : array[0..79] of Char;  
    zoom_hor           : Single;  
    zoom_vert          : Single;  
    imgMilliTimeEx     : SmallInt; // Milliseconds
```

end;

```
TIRBImageData1 = packed record
    geomInfo      : TIRBgeomInfo;
    objectPars    : TIRBobjPars;
    calibPars     : TIRBCalibPars1;
    imgInfo       : TIRBImageInfo;
end;
```

```
PIRBImageData1 = ^TIRBImageData1 ;
```

2.2 IRB-Calib structure

This structure contains data used by calibration:

```
TIRBCalibData = packed record
    Version       : Integer; // Calibration algorithm, there are 8 - Single/float values in IRB-frame
                                //                               9 - model of VarioCAM 2 und ImageIR
    Count         : Integer; // Count of values (version 8 and 9)
    Values        : array [0..269] of Single; // Calibration values
end;
```

If calibration version 8 or 9 is given back, then every array value refers to a temperature value.

2.3 Correction data structure

This structure contains correction data.

```
TIRBCorrPars = packed record
    epsilon : Double;
    envTemp : Double;
    tau     : Double;
    pathTemp : Double;
    lambda  : Double;
    deltaLambda : Double;
end;
```

3 List of DLL-Functions

The irbacs.dll is written with programming language Pascal, so the call convention is stdcall.

3.1 version

Description

Determine Dll-version of the library what can be used for an integrity check.

Function declaration

```
function version( var mainver, subver : Integer ): Boolean;
```

mainver : Main version of the library

subver : Sub-version of the library

Return value

True : Success

False : Error

3.2 loadIRB

Description

Open an IRB file for processing and activates the first available frame.

Function declaration

```
function loadIRB( const fn : PAnsiChar ) : PtrUInt;
```

fn : Full path name of IRB file

Return value

Value > 0 : Reference to internal management structure

Value = 0 : Error

3.3 unloadIRB

Description

Free the internal management structure in the Dll.

Function declaration

```
procedure unloadIRB( const aHandle : PtrUInt );
```

aHandle : With loadIRB created reference

Return value

No return value

3.4 getFrameCount

Description

Get count of frames in IRB-file.

Function declaration

```
function getFrameCount( const aHandle : PtrUInt ): Integer;
```

aHandle : With loadIRB created reference

Return value

Value > 0 : Count of IR frames
Value = 0 : Error

3.5 getIRBIndices

Description

Determine indexes of thermo images in the IRB file, the so called IRB-indexes.

Function Declaration

```
function getIRBIndices( const aHandle : PtrUInt; const irbIdxList : PInteger ): Integer;
```

aHandle : With loadIRB created reference

irbIdxLst : For getting the count of IRB-indexes in the IRB-file pass nil. To allocate appropriate memory it must have the size of index count * SizeOf(int32). If a pointer to that memory is passed, then function getIRBIndices puts all IRB- indexes in it.

Return value

Value > 0 : Count of IRB-indexes in the IRB-file
Value = 0 : Error

3.6 getFrameNumber

Description

Returns the IRB-index of activated thermo image.

Function declaration

```
function getFrameNumber( const aHandle : PtrUInt ): Integer;
```

aHandle : With loadIRB created reference

Return value

Value > 0 : IRB-index of active frame
Value = 0 : Error

3.7 setFrameNumber

Description

Activate the thermo image according to the passed IRB-Index.

Function declaration

```
procedure setFrameNumber( const aHandle : PtrUInt; const frno : Integer );
```

aHandle : With loadIRB created reference
frno : IRB-Index of thermo image to activate

Return value

No return value

Remark:

Success can be checked by a call of setFrameNumber.

3.8 getFrameNbByArrayIdx

Description

Determines 0-based array index of activated thermo image.

Function declaration

```
function getFrameNbByArrayIdx( const aHandle : PtrUInt ) : Integer;
```

aHandle : with loadIRB created reference

Return value

Value > (-1) : Array index of active thermo image (0-based)
Value = (-1) : Error

3.9 setFrameNbByArrayIdx

Description

Activation of thermo image with array index frno.

Function declaration

```
procedure setFrameNbByArrayIdx(const aHandle : PtrUInt; const frno : Integer);
```

aHandle : With loadIRB created reference
frno : Array index of thermo image to activate (0-based)

Return value

No return value

Remark

success of the action can be checked by getFrameNbByArrayIdx

3.10 getTempBBXY

Description

Determine Blackbody-temperature at position (xx,yy) in thermal image

Function declaration

```
function getTempBBXY( const aHandle : PtrUInt; const xx, yy : Integer ) : Double;
```

aHandle : With loadIRB created reference
xx : Column position of measurement point (0-based)
yy : Row position of measurement point (0-based)

Return value

Value > 0 : Temperature in Kelvin,
Value = 0 : Error

3.11 getTempXY

Description

Determine corrected temperature at position (xx,yy) in thermal image

Function declaration

```
function getTempXY( const aHandle : PtrUInt; const xx, yy : Integer ) : Double;
```

aHandle : With loadIRB created reference
xx : Column position of measurement point (0-base)
yy : Row position of measurement point (0-based)

Return value

Value > 0 : Temperature in Kelvin
Value = 0 : Error

3.12 getDigValXY

Description

Determine digital values at position (xx,yy) of a thermal image.

Function declaration

```
function getDigValXY( const aHandle : PtrUInt; const xx, yy : Integer ) : Double;
```

aHandle : With loadIRB created reference
xx : Column position of measurement point (0-based)
yy : Row position of measurement point (0-based)

Return value

Value > 0 : Temperature in Kelvin
Value = 0 : Error

3.13 readPixelData

Description

Get the whole thermal image as a data array of digital values, black body temperatures or corrected temperatures.

Function declaration

```
function readPixelData( const aHandle: PtrUInt; const pData: Pointer; const what: Integer ) : Integer;
```

aHandle : With loadIRB created reference
pData : Pointer to a buffer allocated by the caller. Pass nil to get the needed memory size.
what : kind of array data
 0 – black body temperatures in K (data type Double)
 1 – corrected temperatures in K (data type Double)
 2 – digital values (data type Double)
 3 – black body temperatures in K (Data type Single)

Return value

Value > 0 : Buffer size (byte)
Value = 0 : Error

3.14 readIRBData

Description

Read the activated raw data thermo image, what can be compressed, incl. header.

Function declaration

```
function readIRBData( const aHandle: PtrUInt; const pIRBFrame: PIRBImageData1 ) : Integer;
```

aHandle : With loadIRB created reference
pIRBFrame : Pointer to a buffer allocated by the caller. Pass nil to get the memory size to allocate.

Return value

Value > 0 : Buffer size (byte)
Value = 0 : Error

3.15 readIRBDataUncompressed

Description

Read the activated uncompressed raw data thermo image incl. header

Function declaration

```
function readIRBDataUncompressed( const aHandle : PtrUInt; const pIRBFrame: PIRBImageData1 ) :  
Integer;
```

aHandle : With loadIRB created reference
pIRBFrame : Pointer to a buffer allocated by the caller. Pass nil to get the memory size to allocate.

Return value

value > 0 : buffer size (byte)
value = 0 : error

3.16 convertPixelToKelvin

Description

Converts raw values (digital values) to temperatures by using the internal calibration and the passed correction parameters.

Function declaration

function(const aHandle: PtrUInt; const pData: Pointer; const cnt: Integer; const corrpars: Pointer): Integer;

aHandle : With loadIRB created reference
pData : Source/destination pointer to a buffer allocated by the caller
cnt : Buffer size in Byte (implicating count of data of type Double to convert)
Corrpars : Structure with correction parameters (see above TIRBCorrPars). If nil is passed the internal correction parameters are used.

Return value

value > 0 : Count of converted values
value = 0 : Error

Example:

```
// Load IRB-file
FIrbacsHnd := _irbacs64_loadIRB( filename );

// get the needed memory size
iMemorySize := _irbacs64_readPixelData( FIrbacsHnd, nil, 2 );
Getmem( kelvdat, iMemorySize );

// read raw values of pixels
iMemorySize := _irbacs64_readPixelData( FIrbacsHnd, kelvdat, 2 );

// example manipulation of raw values (values are of type Double)
pDoub := PDouble( kelvdat );
iPixelSize := iMemorySize div SizeOf( Double );
For ii := 0 to iPixelSize -1 do
begin
    pDoub^ := pDoub^ - 10;
    Inc( pDoub);
end;

// set correction parameters
Corrpars.epsilon      := 0.95;
Corrpars.envtemp      := 293.15;    // in K
Corrpars.tau          := 0.8;
Corrpars.pathtemp     := 283.15;    // in K
Corrpars.lambda       := 0;        // 0 -> value of calibration should be used
Corrpars.deltaLambda  := 0;        // 0 -> value of calibration should be used

Res := _irbacs64_convertPixelToKelvin( FIrbacsHnd, kelvdat, iPixelSize,
                                       @corrpars );
```

3.17 getParam

Description

Read a parameter value of type Single (float) of a thermal image.

Function declaration

```
function getParam( const aHandle: PtrUInt; const what: Integer; var aValue: Double ): Boolean;
```

aHandle : With loadIRB created reference

what : Kind of data to read

0 – Image width

1 – Image height

2 – Temperature level in K

3 – Temperature span in K

4 – Emissivity

5 – Distance

6 – Path temperature

7 – Environment temperature

8 – Absorption

9 – IRB-version (100 or 101)

10 – Zoom (1 = 100%)

14 – PixelFormat :

1 = Byte (8 Bit unsigned)

2 = Word / (16 Bit, unsigned)

61572 (0xF084) = Single (float) (32 Bit floating point signed)

15 – Transmission (tau)

16 – Centroid wavelength Lambda

17 – Delta Lambda

18 – Timestamp with milliseconds relative to start of acquisition

19 – timestamp with absolut time (days since 30.12.1899 12.00 , 1 = 1 day)

20 – Lower limit of calibration range in K

21 – Upper limit of calibration range in K

22 – Trigger state

23 – Integration time in µsec

24 – HFOV in °

25 – VFOV in °

26 – Smooth

27 – Camera temperature in K

28 – Sensor temperature in K

29 – Process interface digital values (optional)

30 – Process interface analog value 1 (optional)

31 – Process interface analog value 2 (reserviert)

32 – Process interface analog value 3 (reserviert)

33 – Process interface analog value 4 (reserviert)

34 – Process interface analog value 5 (reserviert)

aValue : Returned parameter value

Return value

True : Success, aValue is valid
False : Error

3.18 setParam

Description

Set a parameter of type Single (float) of a thermal image. If the IRB-frame is saved with saveSingleFrame() these changes will be saved too.

Function declaration

```
function setParam( const aHandle: PtrUInt; const what: Integer; const aValue: Double ) : Boolean;
```

aHandle : With loadIRB created reference

what : see getParam

aValue : Parameter value to set

Return value

True : Success, aValue is valid
False : Error

3.19 getParamS

Description

Read a parameter of type PAnsiChar of a thermal image.

Function declaration

```
function getParamS( const aHandle: PtrUInt; const what: Integer; const aValue: PAnsiChar ) : Boolean;
```

aHandle : With loadIRB created reference

what : Kind of data to read

11 – Camera name

12 - Camera serial number

13 – Objektive name

aValue : Pointer to a buffer with minimal 256 byte (use constant cMaxParamString). Maximal 256 bytes are filled with a zero terminated string.

Return value

True : Success, aValue is valid
False : Error

3.20 getMilliTime

Description

Read millisecond-timestamp of a thermal image.

Function declaration

```
function getMilliTime( const aHandle: PtrUInt ) : Double;
```

aHandle : With loadIRB created reference

Return value

Value > 0 : High resolution timestamp

value = 0 : Error

3.21 getFrameTimeStamp

Description

Read date and time of a thermal image.

Function declaration

```
function getFrameTimeStamp( const aHandle : PtrUInt; var timestamp: TSystemTime ):Boolean;
```

aHandle : With loadIRB created reference

timestamp : TSystemTime-record with the following structure:

```
type TSystemTime = record
  Year: Word;
  Month: Word;
  DayOfWeek: Word;
  Day: Word;
  Hour: Word;
  Minute: Word;
  Second: Word;
  MilliSecond: Word;
end;
```

Return value

Value > 0 : Success, returned timestamp value is valid

Value = 0 : Error

3.22 getIRBCalibData*

Description

Read calibration data of a thermal image.

Function declaration

```
function getIRBCalibData( const aHandle: PtrUInt; var aIRBCalibData: TIRBCalibData ) : Boolean;
```

aHandle : With loadIRB created reference

aIRBCalibData: Calibration data (For description of structure TIRBCalibData please see 2.2 IRB-Calib structure)

Return value

True : Success, IRBCalibData is valid

False : Error

**This function is only for compatibility with older version 1 SDK contained in this interface. There is no longer need for its functionality by function convertPixelToKelvin.*

3.23 getIRBHeader*

Description

Read IRB-header of a thermal image.

Function declaration

```
function getIRBHeader( const aHandle: PtrUInt; var aIRBHeader: TIRBImageData1 ) : Boolean;
```

aHandle : With loadIRB created reference

aIRBHeader : IRB-header data (For description of structure of TIRBImageData1 please see 2.1 IRB-header structures)

Return value

True : Success, aIRBHeader is valid

False : Error

**This function is only for compatibility with older version 1 SDK contained in this interface. There is no longer need for its functionality by function convertPixelToKelvin.*

3.24 setIRBHeader*

Description

Write IRB-header back to thermal image.

Function declaration

```
function setIRBHeader( const aHandle: PtrUInt; const aIRBHeader: TIRBImageData1 ) : Boolean;
```

aHandle : With loadIRB created reference

aIRBHeader : IRB-header data (For description of structure of TIRBImageData1 please see 2.1 IRB-header structures)

Return value

True : Success

False : Error

**This function is only for compatibility with older version 1 SDK contained in this interface. There is no longer need for its functionality by function convertPixelToKelvin.*

3.25 saveSingleFrame

Description

Save an thermal image in a IRB-file with specified name.

Function declaration

```
function saveSingleFrame( const aHandle: PtrUInt; fn : PChar; pIRBFrame: PIRBImageData1 ) : Boolean;
```

aHandle : With loadIRB created reference

fn : Full name with path of IRB-file

pIRBFrame : Pointer to a buffer with IRB-frame, what consists of header plus pixel data (e.g. previously read by readIRBDataUncompressed)or alternatively nil. In this case the activated frame will be saved.

Return value

True : Success

False : Error

3.26 exportVisBitmap

Description

Save visual image of actual thermal image in a file of corresponding format.

Function declaration

```
function exportVisBitmap( const aHandle: PtrUInt; const fn: PAnsiChar ) : Boolean;
```

aHandle : With loadIRB created reference

fn : Full name of bitmap-file to save

Return value

True : Success

False : Error

3.27 audioComment

Description

Save audio comment of actual thermal image as wav-file.

Function declaration

function audioComment(const aHandle: PtrUInt; const fn: PAnsiChar) : Boolean;

aHandle : With loadIRB created reference

fn : Full name of wav-file to save

Return value

True : Success

False : Error